## Pointing System Communication Protocol

The communication protocol used to communicate with the Arduino pointing system software over UART is 4 bytes. These 4 bytes inform the system of correction factors to the z-axis (or azimuth) servo angle. The protocol takes the following illustrated format:

Where S is a sign bit, and V is a value bit. There is technically no restriction to the values that can be sent, however sending nonsensical data will result in nonsensical behavior by the system.

*Note:* this protocol only allows integer value correction factors to be sent.

## Example 1

Rotate z-axis servo by -2 degrees 1002

## Example 2

Rotate z-axis servo by 43 degrees *0043* 

- Max Bowman, 5/07/17
- <u>maxabowman@gmail.com</u>